

Quark v4.1 and earlier for Windows Guideline for PostScript Files

These instructions are intended for files that are one color (black). If your job contains color, please contact Thomson-Shore for further information. The dialog boxes shown in these instructions were generated from a Windows 98 computer.

You must setup a PostScript printer first before making PostScript from Pagemaker. See our guideline for installing a Microsoft PostScript Printer Driver.

Pull down the **FILE** menu and go to **PRINT**.

Select the **DOCUMENT** tab.

For Printer select the Linotronic 530.

In the **COPIES** box type **1**.

In the **PAGES** area, select the range of pages you want to include in the postscript file.

Select the **INCLUDE BLANK PAGES** check box.

Clear all other check boxes.



From the **PAGE SEQUENCE** list, select **ALL**.


From the **REGISTRATION** list, select **CENTERED**.

From the **TILING** list, select **OFF**.

In the **BLEED** box, type in the amount of bleed (.125")

In the **OFFSET** box, type in **12 points**. This is the distance that crop marks will be offset from the edge of the page.





Next select the **SETUP** tab.

The **PRINTER DESCRIPTION** box should have a PostScript printer selected that accommodates the page size you are using. If available, select **LINOTRONIC 530**.

In the **PAPER SIZE** box, use the custom page size and set the **PAPER WIDTH** box to be 1" larger than the final width. **PAPER HEIGHT** is set to Automatic.


REDUCE OR ENLARGE should be set to *100%*.

PAGE POSITIONING should be set to *LEFT EDGE*.

PAGE OFFSET and **PAGE GAP** should be set to *0* (zero).

Clear the **FIT IN PRINT AREA** check box.

ORIENTATION should be set to portrait.




Next select the **OUTPUT** tab.

The **PRINT COLORS** box should be set to *GRAYSCALE*. This will cause any color you have in the document to reproduce as shades of gray.

HALFTONING should be set to *conventional*.

RESOLUTION should be set to *2540*. **FREQUENCY** should be set to *150*.



Next select the **OPTIONS** tab.


Clear all check boxes *except* **FULL RESOLUTION TIFF OUTPUT**. This keeps Quark from downsampling scanned images when the PostScript is written.

PAGE FLIP should be set to *None*.

OUTPUT should be set to *Normal*.

DATA should be set to *Binary*.

OPI should be set to *Include Images*.



This will bring up a dialog box where you can name the file. Give the file a name that will indicate the page range contained in the file. ie. chapter1.prn or pps1-50.prn

Pay attention to the folder where you are saving the file so you know where to find the PostScript file.

Click on OK after naming the file.

This will create a PostScript file. Follow the Acrobat Distiller guidelines for creating PDF files.